

# GenICam ICD FLIR IR Camera - PC

## Contents

|          |                                      |          |
|----------|--------------------------------------|----------|
| <b>1</b> | <b>Connectivity Overview</b>         | <b>2</b> |
| 1.1      | Physical interfaces                  | 2        |
| 1.2      | Low level protocols                  | 2        |
| 1.2.1    | Ethernet                             | 2        |
| 1.3      | Functionality                        | 2        |
| 1.3.1    | GenICam                              | 2        |
| 1.3.2    | IP services                          | 3        |
| <b>2</b> | <b>GenICam Commands</b>              | <b>5</b> |
| 2.1      | Introduction                         | 5        |
| 2.2      | GenICam registers                    | 6        |
| 2.2.1    | Register types                       | 6        |
| 2.2.2    | IP Engine status and control         | 7        |
| 2.2.3    | GigE Vision (GEV) standard interface | 9        |
| 2.2.4    | FLIR Camera interface                | 13       |

## **1** Connectivity Overview

### **1.1** Physical interfaces

The FLIR IR camera, when used for GenICam data transfer, can be used in two ways.

- Dedicated Gigabit Ethernet
- Shared Ethernet

A Dedicated Gigabit Ethernet is recommended for high speed applications and when image streaming would disturb other equipment on a Shared Ethernet.

### **1.2** Low level protocols

On the mentioned physical interface, it is possible to run different low level protocols.

#### **1.2.1** Ethernet

The IP GigEVision streaming protocol is used for image transfer and the GigEVision control protocol is used for camera control.

Some other IP protocols are supported for network management functions. They should work seamlessly on any LAN, provided that a proper IP adress, netmask and possibly gateway is set in the camera.

### **1.3** Functionality

The ethernet communication functionality is provided by an iPORT IP Engine inside the camera. You can use it to manage image streaming and control the camera through the GenICam command control interface.

#### **1.3.1** GenICam

To be able to acquire images and control the camera, you have to have a software environment that meets the specifications of the machine vision standards GigE Vision and GenICam. For more information about this, see <http://www.genicam.org/>.

Such environments are, for example,

- "Measurement and Automation Explorer (MAX)" from National Instruments.
- "EBus Pure GEV SDK" from Pleora Technologies.
- "EBus Vision SDK" from Pleora Technologies.
- "Common Vision Blox" from Stemmer Imaging.

The camera supports the GenICam standard command set, and some FLIR specific commands.

The GenICam Standard Features Naming Convention (available at <http://www.genicam.org/>) is used.

## 1.3.2 IP services

### 1.3.2.1 DHCP

The camera supports the client part of the Dynamic Host Configuration Protocol (DHCP).

### 1.3.2.2 Remote detection

#### 1.3.2.2.1 Multicast DNS (Bonjour)

To query Bonjour for local FLIR IR cameras, use

- Service name: flir-ircam
- Protocol type: \_tcp
- Domain: local

| Name  | Value (example) | Explanation                    |
|-------|-----------------|--------------------------------|
| model | R               |                                |
| ID    | A320G           | Camera ID                      |
| GID   | Gen_A/G         | Generic ID                     |
| SI    | GEV             | Streaming Interface            |
| SIV   | 1.0.0           | Streaming interface version *) |
| CI    | GEV             | Command interface              |
| CIV   | 1.0.0           | Command interface version *)   |

Table 1: TXT records

\*) The version information provided here is (unfortunately) not accurate. You need to check The DeviceManufacturerInfo register.

For more information, see <http://www.dns-sd.org>

#### **1.3.2.2.2** GigEVision Control Protocol (GVCP)

GigEVision camera queries return the model name and MAC address of the cameras found.

For more information, see <http://www.machinevisiononline.org>

## 2 GenICam Commands

### 2.1 Introduction

The goal of GenICam is to provide a generic programming interface for all kinds of cameras.

The GenICam standard consists of multiple modules according to the main tasks to be solved:

- GenApi : GenICam application programming interface (API) for camera configuration and control
- GenTL : GenICam transport layer (TL) for grabbing images

The GenApi module deals with the problem of how to configure and control a camera. The key idea is to make camera manufacturers provide machine readable versions of the manuals for their cameras. These camera description files contain all of the required information to automatically map a camera's features to named *registers*.

The GenTL module is still under construction. Until it is finished, image transfers are made through software environment specific interfaces.

This section defines the GenICam registers of the GigEVision compatible camera.

Inside the FLIR IR camera, there is an iPORT IP Engine. It has a number of status registers and registers that control the way in which it acquires images from the camera.

From the iPORT IP Engine point of view, the FLIR IR camera is regarded as a GigE Vision device with some special FLIR Camera features.

To be able to use these registers to acquire images and control the camera, you have to establish a connection to it through a software environment that meets the specifications of the machine vision standards GigE Vision and GenICam, such as the eBus SDK from Pleora Technologies.

## 2.2 GenICam registers



Depending on the camera model, all registers may not be available or functional on a particular camera.

### 2.2.1 Register types

The registers have one of the following types:

|  |   |
|--|---|
| Integer                                  | An integer value, between -2 147 483 648 and 2 147 483 647.   |
| String<br>(max length<br>including null) | An ASCII string, for example "ThermaCAM".<br>The string must be terminated with a Null (binary 0) character |
| Bool                                     | The integer value 1 for true, or the integer value 0 for false.   |
| Float                                    | An IEEE 754 -1985 encoded floating point value, between $\pm 3.4028235 \times 10^{38}$ .                    |
| Enum                                     | An integer value with a specific encoding.  |
| Cmd                                      | An integer value with a specific encoding used as a command.  |

They can be accessed in one of these three ways:

|    |            |
|----|------------|
| RO | Read only  |
| RW | Read write |
| WO | Write only |

## 2.2.2 IP Engine status and control

To establish a connection through the Pleora Indigo SDK, you have to connect using the IP-number of the camera and retrieve a handle to the map of register nodes. Information about them will automatically be downloaded from the camera.

### 2.2.2.1 Device Information registers

Registers associated with device information

| Name                   | Type        | Access | Comment   |
|------------------------|-------------|--------|---|
| DeviceVendorName       | String (32) | RO     | Provides the name of the manufacturer of the device.            |
| DeviceModelName        | String (32) | RO     | Provides the model of the device.                               |
| DeviceVersion          | String (32) | RO     | Provides the version of the device.                             |
| DeviceManufacturerInfo | String (48) | RO     | Provides extended manufacturer information about the device. *) |
| DeviceID               | String (16) | RO     | This register holds a camera identifier.                        |
| DeviceUserID           | String (16) | RW     | This register holds a user-programmable identifier              |

\*) The DeviceManufacturerInfo register contains six entries separated by commas (Camera ID, Generic ID, Streaming interface, Streaming interface version, Command interface, Command interface version), for example: "A320G, Gen\_A/G, GEV, 1.0.0,GEV,0.2.1".

**2.2.2.2** IP Engine status registers

Registers associated with the IP Engine status

| Name                         | Type    | Access | Comment   |
|------------------------------|---------|--------|---|
| IPEngineFirmwareVersionMajor | Integer | RO     | This register represents the major version of the iPORT IP Engine firmware.   |
| IPEngineFirmwareVersionMinor | Integer | RO     | This register represents the minor version of the iPORT IP Engine firmware.   |
| IPEngineInitSequenceStatus   | Integer | RO     | This register reports the status of the initialization sequence. A null value indicates that the initialization sequence ran successfully. Otherwise, it returns the index of the register write that failed in the sequence. |



## 2.2.3 GigE Vision (GEV) standard interface

### 2.2.3.1 GigE Vision Image size control registers

Registers associated with the image size.

| Name              | Type    | Access | Comment   |
|-------------------|---------|--------|---|
| Width             | Integer | RW     | This register represents the current image width from the camera (in pixels). Mandatory GEV feature.  |
| Height            | Integer | RW     | This register represents the current image height from the camera (in pixels). Mandatory GEV feature.   |
| OffsetX           | Integer | RW     | This register represents the horizontal distance (in pixels) from the center of the detector to the center of the image. This offset plus the current image width cannot exceed the detector width. |
| OffsetY           | Integer | RW     | This register represents the vertical distance (in pixels) from the center of the detector to the center of the image. This offset plus the current image width cannot exceed the detector height.  |
| PixelFormat       | Enum    | RW     | This register indicates the format of the pixel to use during the acquisition. Pixel format as defined in GVSP (the GigE Vision Streaming Protocol). Mandatory GEV feature.                         |
| PayloadSize       | Integer | RO     | Number of bytes transferred for each image on the stream channel. Mandatory GEV feature.  |
| TestImageSelector | Enum    | RW     | This feature selects the type of test image that is created by the GEV interface board.<br>0=Off<br>1= TestPattern  |

### 2.2.3.2 GigE Vision Acquisition control registers

Registers associated with the IP Engine acquisition of images from the camera and their transmission on the ethernet.

| Name                  | Type    | Access | Comment  |
|-----------------------|---------|--------|--|
| AcquisitionFrameCount | Integer | RW     | This register provides the number of frames to be acquired in MultiFrame Acquisition mode.   |
| AcquisitionMode       | Enum    | RW     | This register controls the acquisition mode of the device. Mandatory GEV feature.<br>0=Continuous<br>1=SingleFrame<br>2=MultiFrame |
| AcquisitionStart      | Cmd     | WO     | This register starts the Acquisition of the device. Mandatory GEV feature.   |
| AcquisitionStop       | Cmd     | WO     | This register stops the Acquisition of the device at the end of the current Frame. Mandatory GEV feature.                          |

### 2.2.3.3 GigE Vision Network Configuration registers

Registers associated with the GEV transport protocol.

| Name                                    | Type    | Access | Comment  |
|---|---------|--------|--|
| GevVersionMajor                         | Integer | RO     | This register represents the major version of the GEV specification  |
| GevVersionMinor                         | Integer | RO     | This register represents the minor version of the specification.   |
| GevDeviceModeIsBigEndian                | Bool    | RO     | Endianness might be used to interpret multi-byte data for READMEM and WRITEMEM commands.                           |
| GevDeviceModeCharacterSet               | Enum    | RO     | This register represents the character set used by all the strings of the bootstrap registers.                     |
| GevMACAddressHigh                       | Integer | RO     | This register stores the upper two bytes of the MAC address of the given network interface.                        |
| GevMACAddressLow                        | Integer | RO     | This register stores the lower four bytes of the MAC address of the given network interface.                       |
| GevSupportedIPConfigurationLLA          | Bool    | RO     | This register indicates if Link Local Address IP configuration scheme is supported by the given network interface. |
| GevSupportedIPConfigurationDHCP         | Bool    | RO     | This register indicates if DHCP IP configuration scheme is supported by the given network interface                |
| GevSupportedIPConfigurationPersistentIP | Bool    | RO     | This register indicates if Persistent IP configuration scheme is supported by the given network interface.         |
| GevCurrentIPConfigurationLLA            | Bool    | RW     | This register indicates if Link Local Address IP configuration scheme is activated on the given network interface. |
| GevCurrentIPConfigurationDHCP           | Bool    | RW     | This register indicates if DHCP IP configuration scheme is activated on the given network interface.               |
| GevCurrentIPConfigurationPersistentIP   | Bool    | RW     | This register indicates if PersistentIP configuration scheme is activated on the given network interface           |
| GevCurrentIPAddress                     | Integer | RO     | This register reports the IP address for the given network interface once it has been configured.                  |

| Name                        | Type         | Access | Comment   |
|-----------------------------|--------------|--------|---|
| GevCurrentSubnetMask        | Integer      | RO     | This register provides the subnet mask of the given interface.  |
| GevCurrentDefaultGateway    | Integer      | RO     | This register indicates the default gateway IP address to be used on the given network interface.                       |
| GevFirstURL                 | String (512) | RO     | This register holds the first URL to the XML device description file.   |
| GevSecondURL                | String (512) | RO     | This register holds the second URL to the XML device description file.  |
| GevNumberOfInterfaces       | Integer      | RO     | This register indicates the number of physical network interfaces supported by this device                              |
| GevPersistentIPAddress      | Integer      | RW     | This register indicates the Persistent IP address for this network interface.   |
| GevPersistentSubnetMask     | Integer      | RW     | This register indicates the Persistent subnet mask associated with the Persistent IP address on this network interface. |
| GevPersistentDefaultGateway | Integer      | RW     | This register indicates the persistent default gateway for this network interface.                                      |
| GevHeartbeatTimeout         | Integer      | RW     | This register indicates the current heartbeat timeout in milliseconds.  |
| GevCCP                      | Enum         | RW     | This register is used to grant privilege to an application.<br>0=Open access<br>1=Exclusive access<br>2=Control access  |
| GevSCPIInterfaceIndex       | Integer      | RW     | Index of network interface to use (from 0 to 3).  |

To make the iPort announce network configuration changes on the ethernet, you have to reset the iPort using the FLIR command register PT1000Reset.

## 2.2.4 FLIR Camera interface

### 2.2.4.1 Feature registers

Registers associated with camera features

| Name               | Type    | Access | Comment   |
|--------------------|---------|--------|---|
| CameraCapabilities | Integer | RO     | Camera capabilities. Bit mask.<br>0=Focus, auto focus single shot<br>1=Focus, motor<br>2=Digital I/O capable<br>3=IRWindowing |
| PowerMode          | Enum    | RO     | 0=A/C powered<br>1=Power over Ethernet  |
| PT1000Reset        | Cmd     | WO     | Reset the iPORT interface board.  |

### 2.2.4.2 Range (case) registers

The camera has a list of measurement ranges (called calibration cases) which you can inspect through these registers. You can also make the camera switch to one of them using the CurrentCase register.

There is one set of cases for each lens the camera has been calibrated with. The first lens would normally occupy cases 0, 1 and 2. The second lens cases 3, 4 and 5.

Some cases can be disabled. If the camera doesn't have a high temperature option, cases 2, 5, 8 etc will normally be disabled.

To retrieve data for a particular case, set its number in QueryCase register and read the range data in the QueryCaseXXXX registers.

Switching cases is quite a slow procedure. It can take up to 10 seconds. If it fails, the CurrentCase will eventually return to the previous value.

| Name               | Type    | Access | Comment   |
|--------------------|---------|--------|---|
| NumCases           | Integer | RO     | Number of available cases   |
| CurrentCase        | Integer | RW     | Current zero based case.  |
| QueryCase          | Integer | RW     | Query case zero based index.<br>This register controls the content of QueryCaseLowLimit, QueryCaseHighLimit and QueryCaseEnabled. |
| QueryCaseLowLimit  | Float   | RO     | Queried case low limit in Kelvin.   |
| QueryCaseHighLimit | Float   | RO     | Queried case high limit in Kelvin.  |
| QueryCaseEnabled   | Bool    | RO     | True if the queried case is enabled.  |

Date  
3/4/12

---

### 2.2.4.3 Object Parameter registers

Registers associated with infrared measurement conditions.

| Name                   | Type  | Access | Comment                                   |
|------------------------|-------|--------|---|
| ReflectedTemperature   | Float | RW     | Kelvin, 0.0 - 5000.0                      |
| AtmosphericTemperature | Float | RW     | Kelvin, 0.0 - 5000.0                      |
| ObjectDistance         | Float | RW     | Meter, 0.0 - 10000.0                      |
| ObjectEmissivity       | Float | RW     | 0.0 - 1.0                                 |
| RelativeHumidity       | Float | RW     | Percent, 0.0 - 100.0                      |
| ExtOpticsTemperature   | Float | RW     | Kelvin, 0.0 - 5000.0                      |
| ExtOpticsTransmission  | Float | RW     | 0.0 - 1.0                                 |
| EstimatedTransmission  | Float | RW     | 0.01 - 1.0<br>0.0 = Use calculated value. |

**2.2.4.4** Focus registers

Registers associated with camera focus operation

| Name            | Type    | Access | Comment   |
|-----------------|---------|--------|---|
| FocusSpeed      | Integer | RW     | 0 to 100 (0 = permanent stop)   |
| FocusDirection  | Enum    | RW     | Stop = 0<br>Far = 1<br>Near = 2   |
| AutoFocusMethod | Enum    | RW     | 0=Coarse<br>1=Fine  |
| AutoFocus       | Cmd     | WO     | Perform auto focus operation.   |
| FocusPos        | Integer | RW     | Absolute focus position<br>A high value means a far distance on some types of cameras, a near distance on others.   |
| FocusDistance   | Float   | RW     | Focus position as distance in meters *)<br>Min = 0<br>Max = 1000  |
| FocusStep       | Integer | RW     | Absolute focus position change amount for FocusDecrement and FocusIncrement. *)<br>Small values (<250) might not move the focus.<br>Min = 0<br>Max = 1000 |
| FocusDecrement  | Cmd     | WO     | Decrements the focus position by the value in FocusStep *)  |
| FocusIncrement  | Cmd     | WO     | Increments the focus position by the value in FocusStep *)  |

\*) Needs command interface version 0.2.12. See the DeviceManufacturerInfo register



### 2.2.4.5 Image quality registers

Registers associated with the image quality

| Name           | Type | Access | Comment   |
|----------------|------|--------|---|
| NoiseReduction | Enum | RW     | 0 = Off<br>1 = Low etc.   |
| NUCMode        | Enum | RW     | Non-Uniform Correction (NUC) mode<br>Off = 0<br>Automatic by camera=1 |
| NUCAction      | Cmd  | WO     | Do NUC operation.<br>This can take up to 10 seconds.                  |

### 2.2.4.6 Image stream registers

Registers associated with the image format or with the image stream..

| Name          | Type | Access | Comment   |
|---------------|------|--------|---|
| IRFormat      | Enum | RW     | 0=Signal linear<br>1=Temperature linear, 0.1K resolution<br>2=Temperature linear, 0.01K resolution  |
| IRTestPattern | Enum | RW     | This register selects the type of test image that is created by the IR camera.<br>0=Off (see IRFormat)<br>1= TestPattern  |
| IRFrameRate   | Enum | RW     | Camera model dependent values, normal non-windowing examples:<br>0= 60Hz/50Hz<br>1= 30Hz/25Hz<br>2= 15Hz/12.5Hz<br>...<br>The availability of some frame rates can depend on the image width, height and offset settings.<br>When IRWindowing is used, the frame rate increases by the same amount as the image height decreases. |
| IRWindowing   | Enum | RW     | This register can only be changed when no streaming is going on. It moves the vertical start of the image and changes the frame rate. You must change the "Height" register accordingly.<br>0=Off (Full height, normal rate)<br>1=Half (Half height, double rate)<br>2=Quarter (Quarter height, fourfold rate)                    |

The image pixels are transferred left to right, row by row, from top to bottom. The byte order is in accordance with the `GevDeviceModelIsBigEndian` register.

Date  
3/4/12

### 2.2.4.7 External I/O registers

Registers associated with configuring camera external I/O ports.

| Name                 | Type    | Access | Comment   |
|----------------------|---------|--------|---|
| NumPorts             | Integer | RO     | Number of available I/O ports.  |
| CurrentPort          | Integer | RW     | Current selected I/O port. Zero based index.  |
| CurrentIOType        | Enum    | RO     | Type of I/O port<br>0=Digital<br>1=Analog   |
| CurrentIODirection   | Enum    | RO     | 0=Input<br>1=Output<br>2=Bi-directional   |
| CurrentIOConfig      | Integer | RW     | Port function configuration.<br>0=General Purpose<br>1=Vertical sync (output only)<br>2=Set Mark in IR image (input only)<br>3=Set Start mark in IR image (input only)<br>4=Set Stop mark in IR image (input only)<br>5=Enable image flow (input only)<br>6=Disable image flow (input only) |
| CurrentIOPolarity    | Enum    | RW     | Output port polarity<br>0=Active High<br>1=Active Low   |
| CurrentIOSensitivity | Enum    | RW     | Input port edge sensitivity<br>(IOConfig 2,3,4, 5 and 6 only)<br>0=Rising edge<br>1=Falling edge<br>2=Both rising and falling edge  |
| CurrentIOState       | Enum    | RW     | Current I/O port state<br>0=Deasserted<br>1=Asserted  |

The CurrentIOConfig Vertical sync output configuration provides a short pulse (about 150  $\mu$ s) whenever a new image starts.